

Useful keyboard shortcuts

Function keys

[F1]	In the work environment: opens IntelliCAD Help / In the visualization: turns on the lights
[F2]	Opens the operation history preview
[F3]	Enables or disables the cursor snap function (ESNAP)
[F4]	Enables or disables the tablet
[F7]	Enables or disables the GRID (grid points in every 500 mm)
[F8]	Enables or disables the ORTHO mode (drawing at right angles)
[F9]	Enables or disables the cursor jump function (SNAP - set to 1 mm)
[F10]	Shows or hides the Status Bar
[F11]	Opens the quick preview of visualization
[F12]	Opens the visualization

Mouse

[Ctrl] + [left button]	Rotates the view in 3D
[Ctrl] + [right button]	Rotates the view in 2D
[Ctrl] + [Shift] + [left button]	Zooms the current view in or out (in real time)
[Ctrl] + [Shift] + [right button]	Moves the current view (in real time)
[Scroll wheel pressed, mouse moved]	Moves the current view (in real time)
[Scroll wheel rolled]	Zooms the current view in or out
[Scroll wheel double clicked]	Sets the central view at the entire drawing

Shortcuts

[Ctrl]+[Z]	Undoes operations (in CAD environment: to the very beginning, in visualization: 20 latest)
[Ctrl]+[Y]	Redoes undone operations
[Ctrl]+[S]	Saves the drawing
[Ctrl]+[O]	Opens the drawing
[Ctrl]+[N]	Creates a new drawing
[E]>>[Enter] or [Del]	Deletes the element
[CO]>>[Enter] or [Space]	Copies the element
[M]>>[Enter] or [Space]	Moves the element
[X]>>[Enter] or [Space]	Splits the element
[RE]>>[Enter] or [Space]	Regenerates the drawing
[U]>>[Enter] or [Space]	Undoes the last step during drawing (using any drawing tool)
[Enter] or [Space] or [right mouse button]	Ends the current or repeats the last operation
[Esc]	Terminates or ends the current operation, closes the window (canceling the changes)

While drawing paths

[A]>>[Enter] or [Space]	Switches to drawing arcs, based on 2 points
[S]>>[Enter] or [Space]	Switches from drawing arcs based on 2 points to drawing arcs based on 3 (user indicated 3 points: starting, second - to go through, and ending)
[L]>>[Enter] or [Space]	Switches to drawing straight lines
[C]>>[Enter] or [Space]	Closes the path (note: option inactive in the arc-drawing mode)